

GRID storage access tools installation

The following documentation was developed for the installation of a GRID tools and certificates on an Ubuntu 12.04 system using a bash shell (using `.bashrc` as a configuration script). We have not tested the installation using `csh` derivatives but it is to be expected that not all scripts will work. Thanks to Martin van den Akker for providing notes of his installation procedure.

Sites that provide packages and further information on installation of grid middleware on linux based systems:

- [Software repository of the European Grid Infrastructure](#)
- [Initiative for Globus in Europe](#)
- [Home of the gLite software suite](#) (gLite UI provides a typical client installation)

NB Only the Ubuntu 12 installation described below has been tested by us. Please let us know if you have feedback or if you can contribute instructions on installations in different environments. You might also first need to obtain a [GRID certificate](#).

Installation of software packages

Note: all installations require root permissions.

globus client software

The file transfer tools from the Globus package are needed, most importantly `globus-url-copy`:

```
sudo apt-get install globus-gass-copy-progs
```

voms client software

The VOMS tools for logging in and user account management:

```
sudo apt-get install voms-clients
```

Certificates for the Grid Certificate Authorities (CA)

Execute the following commands to install the certificates from the site of the European Grid Infrastructure (EGI) (root permissions are required).

```
sudo add-apt-repository 'deb
http://repository.egi.eu/sw/production/cas/1/current egi-igtf core'
sudo apt-get update
sudo apt-get install ca-policy-egi-core
```

srmtools

The SRM tools are needed to communicate with the storage management system.

1. Download srmtools
 - srm.tar.gz
2. Extract and install the srmtools, e.g. in /opt/
This will create a subdirectory srm containing the required files.
Note that the srm package may be installed anywhere (e.g. in your home directory).
3. Set the relevant environment path variables, e.g. in .bashrc:

```
export SRM_PATH=<Install Directory>/srm
export PATH=$SRM_PATH/bin:$PATH
```

NB The srm client tools depend on JAVA. There is a known issue with openjava version 7. If you have this version of JAVA installed, or otherwise get JAVA exceptions when running an srm command, please install another JAVA VM. java-6-openjdk is known to work. It is possible to have multiple JAVA VM installations and it is thus not required to replace an existing installation: if the default VM installation does not work with srm, another VM may be configured to be used by setting the following environment parameter:

```
export JAVA_HOME=/usr/lib/jvm/java-6-openjdk-i386/jre
```

The JAVA VM used by default in Ubuntu can be selected using the following command:

```
sudo update-alternatives --config java
```

Certificate Revocation List retrieval (optional)

The fetch-crl tool retrieves Certificate Revocation Lists.

```
sudo apt-get install fetch-crl
```

NB This is not required unless you intend to allow others to access your system by providing their grid certificate.

Additional configuration

VOMSES file for LOFAR

Add the following string for the LOFAR Virtual Organization (VO) to the vomses file.

```
"lofar" "voms.grid.sara.nl" "30019"
"/0=dutchgrid/0=hosts/0U=sara.nl/CN=voms.grid.sara.nl" "lofar"
```

You can find this string also on the following website

<https://voms.grid.sara.nl:8443/voms/lofar/configuration/configuration.action> in the text block under *VOMSES string for this VO*

The vomses file should be placed in one of the following default locations: /etc/vomses, \$HOME/.voms/vomses, \$HOME/.glite/vomses

List of certificates for voms.grid.sara.nl.lsc

Put the following strings:

```
/O=dutchgrid/O=hosts/OU=sara.nl/CN=voms.grid.sara.nl  
/C=NL/O=NIKHEF/CN=NIKHEF medium-security certification auth
```

in the file (root permissions required):

```
/etc/grid-security/vomsdir/lofar/voms.grid.sara.nl.lsc
```

NB If this step is skipped or not configured correctly voms-proxy-init will work but finish with warnings.

Environment (optional)

You may want to provide the following settings in .bashrc or another initialisation/startup script if the relevant files are not in the default locations (defaults provided below).

```
export X509_USER_CERT=$HOME/.globus/usercert.pem  
export X509_USER_KEY=$HOME/.globus/userkey.pem  
export X509_CERT_DIR=/etc/grid-security/certificates  
export X509_VOMS_DIR=/etc/grid-security/vomsdir  
export VOMS_USERCONF=$HOME/.glite
```

CRL cron job (optional)

You may want to create a cron job to automatically retrieve certificate revocation lists (CRLs) by incoking the fetch-crl tool at regular intervals (at least once a year).

From:
<https://www.astron.nl/lofarwiki/> - **LOFAR Wiki**

Permanent link:
https://www.astron.nl/lofarwiki/doku.php?id=public:grid_srm_software_installation&rev=1387476075

Last update: **2013-12-19 18:01**

